

Pfast 2.1 Installation Instructions

1. Save the **Pfast21Setup.zip** file to your computer (make a note of the location of the zip file).

These steps apply to a computer with the Windows 7/10 operating system. If you have a different operating system or have an application like WinZip installed the process will vary somewhat.

2. Find the **Pfast21Setup.zip** you downloaded to your computer.
3. Place your cursor (pointer) over the file.
4. Right-click and select **Extract All...**
5. Click in the box below **Files will be extracted to this folder:**
6. Type **C:\CCAD Add ons**.
7. Remove the check mark from **Show extracted files when complete**.
8. Choose the **Extract** button.

Note: You must extract the files from the zip file as AutoCAD will not open files from a zip file.

AutoCAD 2006+ Installation

1. Begin AutoCAD.
2. Type Options and press ENTER.
3. Click the Files Tab.
4. Expand the Support File Search Path icon by clicking on the + symbol.
5. Click the Add... button. **DO NOT FORGET THIS STEP!**
6. Click the Browse... button.
7. Navigate to the C:\CCAD Add ons folder (or folder you made/selected).
8. Click on C:\CCAD Add ons and click OK.

AutoCAD 2014+ ONLY (8a-8e)

- 8a. Expand the Trusted Locations icon by clicking on the + symbol.
- 8b. Click the Add... button.
- 8c. Click the Browse... button.
- 8d. Navigate to the C:\CCAD Add ons folder (or folder you selected).
- 8e. Click on C:\CCAD Add ons and click OK (or folder you made/selected).

9. Click on the **OK** button when finished.
10. Type **Cuiload** and press **ENTER**. *If 2005 or older Type **Menuload** and press **ENTER**.*
11. Select **Browse...** and locate the **C:\CCAD Add ons** folder (or folder you selected).
12. Double-click on **C:\CCAD Add ons** (or folder you selected).
13. Double-click the **Pfast.cui(x)** file. *If 2005 or older Double-click the **Pfast.mns** file.*
14. Select the **Load** button and close the window.

If your toolbar isn't displayed, do the following:

Place your cursor in the blank space of a toolbar docking area or type **-toolbar**, press ENTER, type **PFAST**, press **ENTER** type **SHOW** and press **ENTER**.

If your ribbon tab isn't displayed, do the following:

Place your cursor over a ribbon tab. Right-click and select **Show tabs**. Click **Pfast 2.1**.